

Code Documentation

Overview

This software implements a two-model approach for person detection in images, focusing specifically on thermal imagery. The system first uses a primary model (Model 1) to detect people, and based on confidence thresholds, it either accepts the detection, runs a secondary verification model (Model 2), or rejects the detection entirely. The system incorporates advanced techniques including data augmentation and inpainting for improved detection performance.

Model Architecture

Model 1: Person-Only Detection

- **Purpose:** Primary detection of people in thermal images
- **Classes:** 1 class ('person')
- **Training Data:** Located at [D:/project_work/model1/dataset/train](#)
- **Validation Data:** Located at [D:/project_work/model1/dataset/valid](#)
- **Test Data:** Located at [D:/project_work/model1/dataset/test](#)

Model 2: Body Part Detection

- **Purpose:** Secondary detection and verification of people by identifying body parts
- **Classes:** 5 classes ('arm', 'head', 'leg', 'person', 'torso')
- **Training Data:** Located at [D:/project_work/model_3/dataset/train](#)
- **Validation Data:** Located at [D:/project_work/model_3/dataset/valid](#)
- **Test Data:** Located at [D:/project_work/model_3/dataset/test](#)

Software Requirements

Core Dependencies

- Python 3.7+
- PyTorch 1.7.0+
- TorchVision 0.8.1+
- OpenCV (cv2) 4.5.0+
- NumPy 1.19.0+
- YOLOv5 (will be installed via torch.hub)

Pre-trained Models

- Model 1: YOLOv5 model trained for person detection
 - Path: [D:/project_work/model_1/yolov5/runs/train/model1_train2/weights/best.pt](#)
- Model 2: YOLOv5 model trained for body part detection
 - Path: [D:/project_work/model_3/yolov5/runs/train/exp3/weights/best.pt](#)

Data Preparation & Augmentation

Data Augmentation Techniques

Both models utilized extensive data augmentation as specified in their YAML configuration files:

- **Color Transformations:**
 - HSV-Hue: ± 0.015 fraction
 - HSV-Saturation: ± 0.7 fraction
 - HSV-Value: ± 0.4 fraction
- **Geometric Transformations:**
 - Translation: ± 0.1 fraction
 - Scale: ± 0.5 gain
 - Left-right flip: 0.5 probability
 - Mosaic augmentation: 1.0 probability (always applied)

Inpainting

The system incorporates inpainting techniques to enhance detection performance:

- Inpainted images were added to the training data
- The test example ([inpainted_result1.jpg](#)) is an inpainted thermal image
- Inpainting helps reduce noise and enhance person features in thermal imagery

Model Training Configurations

Common Training Parameters

Both models were trained with similar hyperparameters:

- **Image Size:** 640×640 pixels
- **Batch Size:** 16
- **Training Epochs:** 150
- **Patience:** 100 epochs

- **Optimizer:** SGD
 - Initial learning rate: 0.01
 - Final learning rate factor: 0.01
 - Momentum: 0.937
 - Weight decay: 0.0005
- **Warmup:**
 - Epochs: 3.0
 - Initial momentum: 0.8
 - Initial bias learning rate: 0.1

Model-Specific Parameters

- **Frozen Layers:** First layer [0] frozen during training
- **Loss Parameters:**
 - Box loss gain: 0.05
 - Classification loss gain: 0.5
 - Object loss gain: 1.0
 - IoU training threshold: 0.20

Ensemble Detection System

Logic Flow

The system operates based on the following confidence thresholds:

1. **Model 1 Detection:**
 - If confidence > 90%: Accept detection, display result, and exit
 - If confidence between 85-90%: Output "person not detected properly" and run Model 3
 - If confidence < 85%: Run Model 3 without notification
2. **Model 2 Detection** (when needed):
 - If confidence \geq 85%: Accept detection and display result
 - If confidence < 85% or no detection: Output "no living person detected"

Detection Parameters

- **Confidence Threshold:** 0.25 (during model training)
- **IoU Threshold:** 0.4 (for Non-Maximum Suppression)
- **Maximum Detections:** 300 per image

Setup Instructions

Install Python Dependencies:

`pip install torch torchvision opencv-python numpy`

1. `pip install torch torchvision opencv-python numpy`
2. **Model Paths:** Ensure both models are available at the specified paths:
 - Model 1: `D:/project_work/model_1/yolov5/runs/train/model1_train2/weights/best.pt`
 - Model 2: `D:/project_work/model_3/yolov5/runs/train/exp3/weights/best.pt`
3. Update the paths in the code if your models are stored in different locations.
4. **Test Image:** Place your test image at the specified path or update the image path in the code:
 - Default path: `D:/project_work/model_3/inpainting/inpainted_result1.jpg`

Execution Instructions

Running the Program:

`python person_detection.py`

1. `python person_detection.py`
2. **Output Interpretation:**
 - The program will display console messages indicating detection confidence
 - When a person is successfully detected, a window will appear showing the image with bounding boxes
 - Results will be saved as image files in the current directory
3. **Result Files:**
 - `high_confidence_result.jpg`: Results from Model 1 with high confidence
 - `model2_verification_result.jpg`: Results from Model 2 when used for verification
 - `model2_result.jpg`: Results from Model 2 when used as primary detector

Code Structure

Main Components

1. **Model Loading Functions:**
 - `run_model1()`: Loads and runs the primary person detection model
 - `run_model2()`: Loads and runs the secondary verification model (Model 2)
2. **Visualization Function:**

- `draw_box()`: Handles drawing bounding boxes with labels on detected persons
- 3. Main Execution Function:**
- `main()`: Orchestrates the detection workflow based on confidence thresholds

Complete Code

```
import torch
import numpy as np
import cv2
from torchvision.ops import nms

def run_model1(img_path):
    # Load model1 which detects people
    model1 = torch.hub.load('ultralytics/yolov5', 'custom',
path='D:/project_work/model_1/yolov5/runs/train/model1_train2/weights/best.pt')
    model1.eval()

    # Run inference
    results1 = model1(img_path)

    # Get predictions from model 1
    boxes1 = results1.xyxy[0].cpu().numpy() # Using xyxy format

    # Filter for only person class if needed
    # Assuming "person" is one of the classes - adjust class_id if different
    person_boxes = []
    person_scores = []

    for box in boxes1:
        class_id = int(box[5])
        if results1.names[class_id] == 'person': # Filter for person class
            person_boxes.append(box[:4]) # x1, y1, x2, y2
            person_scores.append(box[4]) # Confidence score

    # If no persons detected
    if not person_scores:
        return None, None, None

    # Find the highest confidence score
    max_score = max(person_scores) if person_scores else 0
    max_index = person_scores.index(max_score) if person_scores else -1

    if max_index != -1:
```

```

        return max_score, person_boxes[max_index], results1.names
    else:
        return None, None, None

def run_model2(img_path):
    # Load model2 which is the backup model (Model 3)
    model2 = torch.hub.load('ultralytics/yolov5', 'custom',
path='D:/project_work/model_3/yolov5/runs/train/exp3/weights/best.pt')
    model2.eval()

    # Run inference
    results2 = model2(img_path)

    # Get predictions from model 2
    boxes2 = results2.xyxy[0].cpu().numpy()

    # Filter for only person class if needed
    person_boxes = []
    person_scores = []

    for box in boxes2:
        class_id = int(box[5])
        if results2.names[class_id] == 'person': # Filter for person class
            person_boxes.append(box[:4]) # x1, y1, x2, y2
            person_scores.append(box[4]) # Confidence score

    # If no persons detected
    if not person_scores:
        return None, None, None

    # Find the highest confidence score
    max_score = max(person_scores) if person_scores else 0
    max_index = person_scores.index(max_score) if person_scores else -1

    if max_index != -1:
        return max_score, person_boxes[max_index], results2.names
    else:
        return None, None, None

def draw_box(image, box, label, score):
    image_height, image_width = image.shape[:2]
    x1, y1, x2, y2 = int(box[0]), int(box[1]), int(box[2]), int(box[3])

    # Ensure coordinates are within image bounds

```

```

x1 = max(0, min(x1, image_width - 1))
y1 = max(0, min(y1, image_height - 1))
x2 = max(0, min(x2, image_width - 1))
y2 = max(0, min(y2, image_height - 1))

cv2.rectangle(image, (x1, y1), (x2, y2), (0, 255, 0), 2) # Draw green rectangle

# Add label and confidence score
label_text = f"{label}: {score:.2f}"
cv2.putText(image, label_text, (x1, y1 - 10), cv2.FONT_HERSHEY_SIMPLEX, 0.5, (0, 255, 0), 2)

return image

def main():
    # Example image path
    img_path = 'D:/project_work/model_3/inpainting/inpainted_result1.jpg'

    # Load the image
    image = cv2.imread(img_path)
    if image is None:
        print(f"Error: Could not load image at {img_path}")
        return

    # First, run model 1
    print("Running model 1 (person detection)...")
    conf_score1, best_box1, names1 = run_model1(img_path)

    if conf_score1 is None:
        print("No person detected by model 1.")
        print("No living person detected.")
        return

    # Check confidence thresholds for model 1
    if conf_score1 >= 0.90: # Above 90%
        print(f"Person detected with high confidence: {conf_score1:.2f}")
        # Draw the bounding box
        result_image = draw_box(image.copy(), best_box1, "person", conf_score1)
        cv2.imshow('Person Detection Result (Model 1)', result_image)
        cv2.waitKey(0)
        cv2.destroyAllWindows()
        cv2.imwrite('high_confidence_result.jpg', result_image)

    elif 0.85 <= conf_score1 < 0.90: # Between 85-90%
        print(f"Person not detected properly in model 1. Confidence: {conf_score1:.2f}")

```

```

print("Running model 2 to verify...")

# Run model 2 for verification
conf_score2, best_box2, names2 = run_model2(img_path)

if conf_score2 is not None:
    print(f"Person detected by model 2 with confidence: {conf_score2:.2f}")
    # Draw the bounding box from model 2
    result_image = draw_box(image.copy(), best_box2, "person", conf_score2)
    cv2.imshow('Person Detection Result (Model 2)', result_image)
    cv2.waitKey(0)
    cv2.destroyAllWindows()
    cv2.imwrite('model2_verification_result.jpg', result_image)
else:
    print("No person detected by model 2.")
    print("No living person detected.")

else: # Below 85%
    print(f"Low confidence person detection: {conf_score1:.2f}")
    print("Running model 2 for verification...")

# Run model 2
conf_score2, best_box2, names2 = run_model2(img_path)

if conf_score2 is not None and conf_score2 >= 0.85:
    print(f"Person detected by model 2 with confidence: {conf_score2:.2f}")
    # Draw the bounding box from model 2
    result_image = draw_box(image.copy(), best_box2, "person", conf_score2)
    cv2.imshow('Person Detection Result (Model 2)', result_image)
    cv2.waitKey(0)
    cv2.destroyAllWindows()
    cv2.imwrite('model2_result.jpg', result_image)
else:
    # Either no person detected or confidence below 0.85
    print("No living person detected.")

if __name__ == "__main__":
    main()

```

Model YAML Configurations

Model 1 Configuration (data.yaml)

YOLOv5 Thermal Body Part Detection Configuration

Train/val/test sets

train: D:/project_work/model1/dataset/train

val: D:/project_work/model1/dataset/valid

test: D:/project_work/model1/dataset/test

Classes

nc: 1 # number of classes

names: ['person'] # class names

Hyperparameters optimized for thermal body part detection

hyp:

Augmentation parameters

hsv_h: 0.015 # HSV-Hue augmentation (fraction)

hsv_s: 0.7 # HSV-Saturation augmentation (fraction)

hsv_v: 0.4 # HSV-Value augmentation (fraction)

degrees: 0.0 # image rotation (+/- deg)

translate: 0.1 # image translation (+/- fraction)

scale: 0.5 # image scale (+/- gain)

shear: 0.0 # image shear (+/- deg)

perspective: 0.0 # image perspective (+/- fraction)

flipud: 0.0 # image flip up-down (probability)

fliplr: 0.5 # image flip left-right (probability)

mosaic: 1.0 # image mosaic (probability)

mixup: 0.0 # image mixup (probability)

Model parameters

box: 0.05 # box loss gain

cls: 0.5 # cls loss gain

cls_pw: 1.0 # cls BCELoss positive_weight

obj: 1.0 # obj loss gain

obj_pw: 1.0 # obj BCELoss positive_weight

iou_t: 0.20 # IoU training threshold

anchor_t: 4.0 # anchor-multiple threshold

fl_gamma: 0.0 # focal loss gamma

Anchors

anchors: 3 # number of anchors per scale

Detection parameters

conf_thres: 0.25 # confidence threshold

iou_thres: 0.4 # NMS IoU threshold

max_det: 300 # maximum detections per image

```

# Image size and batch parameters
img_size: 640    # image size
batch_size: 16   # batch size

# Training parameters
epochs: 150      # number of epochs
patience: 100   # epochs to wait for no observable improvement
freeze: [0]      # freeze first layer during training

# Optimizer parameters
optimizer: SGD   # optimizer: ['SGD', 'Adam', 'AdamW']
lr0: 0.01        # initial learning rate
lrf: 0.01        # final learning rate (lr0 * lrf)
momentum: 0.937  # SGD momentum/Adam beta1
weight_decay: 0.0005 # optimizer weight decay
warmup_epochs: 3.0 # warmup epochs
warmup_momentum: 0.8 # warmup initial momentum
warmup_bias_lr: 0.1 # warmup initial bias lr

```

Model 2 Configuration (data.yaml)

```

# YOLOv5 Thermal Body Part Detection Configuration
# Train/val/test sets
train: D:/project_work/model_3/dataset/train
val: D:/project_work/model_3/dataset/valid
test: D:/project_work/model_3/dataset/test
# Classes
nc: 5 # number of classes
names: ['arm', 'head', 'leg', 'person', 'torso'] # class names
# Hyperparameters optimized for thermal body part detection
hyp:
  # Augmentation parameters
  hsv_h: 0.015 # HSV-Hue augmentation (fraction)
  hsv_s: 0.7   # HSV-Saturation augmentation (fraction)
  hsv_v: 0.4   # HSV-Value augmentation (fraction)
  degrees: 0.0 # image rotation (+/- deg)
  translate: 0.1 # image translation (+/- fraction)
  scale: 0.5   # image scale (+/- gain)
  shear: 0.0   # image shear (+/- deg)
  perspective: 0.0 # image perspective (+/- fraction)
  flipud: 0.0   # image flip up-down (probability)
 fliplr: 0.5   # image flip left-right (probability)
  mosaic: 1.0   # image mosaic (probability)

```

```
mixup: 0.0 # image mixup (probability)
# Model parameters
box: 0.05 # box loss gain
cls: 0.5 # cls loss gain
cls_pw: 1.0 # cls BCELoss positive_weight
obj: 1.0 # obj loss gain
obj_pw: 1.0 # obj BCELoss positive_weight
iou_t: 0.20 # IoU training threshold
anchor_t: 4.0 # anchor-multiple threshold
fl_gamma: 0.0 # focal loss gamma
# Anchors
anchors: 3 # number of anchors per scale
# Detection parameters
conf_thres: 0.25 # confidence threshold
iou_thres: 0.4 # NMS IoU threshold
max_det: 300 # maximum detections per image
# Image size and batch parameters
img_size: 640 # image size
batch_size: 16 # batch size
# Training parameters
epochs: 150 # number of epochs
patience: 100 # epochs to wait for no observable improvement
freeze: [0] # freeze first layer during training
# Optimizer parameters
optimizer: SGD # optimizer: ['SGD', 'Adam', 'AdamW']
lr0: 0.01 # initial learning rate
lrf: 0.01 # final learning rate (lr0 * lrf)
momentum: 0.937 # SGD momentum/Adam beta1
weight_decay: 0.0005 # optimizer weight decay
warmup_epochs: 3.0 # warmup epochs
warmup_momentum: 0.8 # warmup initial momentum
warmup_bias_lr: 0.1 # warmup initial bias lr
```

Customization Options

Adjusting Confidence Thresholds

Modify these values in the `main()` function to adjust sensitivity:

- High confidence threshold (currently 0.90)
- Medium confidence threshold (currently 0.85)

Using Different Models

To use different YOLOv5 models:

1. Update the model paths in the `run_model1()` and `run_model2()` functions
2. Ensure the models are trained to detect the appropriate classes

Processing Multiple Images

To process multiple images:

1. Create a list of image paths
2. Loop through the list and call `main()` for each image
3. Modify the output file naming scheme to avoid overwriting

Troubleshooting

Common Issues and Solutions

1. **Model Loading Error:**
 - Ensure the model paths are correct
 - Verify you have internet access for the first run (YOLOv5 will download dependencies)
2. **No Detection:**
 - Check if the image contains clearly visible persons
 - Adjust confidence thresholds if detections are being filtered out
3. **CUDA/GPU Issues:**
 - Add `device = torch.device('cuda' if torch.cuda.is_available() else 'cpu')`
 - Pass `device` parameter to model loading functions
4. **Memory Issues:**
 - Reduce image size before processing
 - Use `model.half()` for reduced memory usage with slight accuracy loss
5. **Inpainting Issues:**
 - Ensure inpainted images maintain the thermal characteristics
 - Check that inpainting doesn't remove critical features for detection